

# X Linux

:

1. .

```
sudo dpkg-reconfigure intellect-x
```

2. ID, . , Enter.

ITV Intellect X Server Configuration

Leave this blank if you want this host to join an existing Intellect X domain later or set to the \_\_KEEP\_\_ to keep the value unmodified (if any).  
Enter Intellect X domain this host to proclaim.

KEEP

<Ok>

3. .

ITV Intellect X Server Configuration

Name that uniquely identifies the installed server within Intellect X domain. Leave this blank to have the value initialized from the host name or set to the \_\_KEEP\_\_ to keep the value unmodified (if any).  
Intellect X server node name

UBUNTU

<Ok>

4. .

ITV Intellect X Server Configuration

This port is used to determine base port of a TCP port span for Intellect X applications. You may need to change this value if you run several instances of Intellect X on the same host.  
TCP port - base for Intellect X TCP ports range

20111

<Ok>

5. .

ITV Intellect X Server Configuration

In addition to the base port it determines TCP ports range used by Intellect X applications.  
Intellect X TCP ports span

100

<Ok>

6. X. :

- a. "0.0.0.0/0" .
- b. "10.0.1.23/32,192.168.0.7/32" .
- c. "127.0.0.1" .

ITV Intellect X Server Configuration

Comma-separated list of network interfaces in CIDR notation for ITV Intellect X to listen on. Leave it empty if Intellect X is supposed to use all available network interfaces.  
List of network interfaces for Intellect X to listen on.

<Ok>

7. , NAT. : "IP-1 DNS-1, IP-2 DNS-2".

ITV Intellect X Server Configuration

It may be used to specify public address for ITV Intellect X when access a server working behind the NAT from outside. Appropriate port forwarding must be set up on the NAT itself in order to make this option work. Leave it empty if unsure or the server is not supposed to be accessed from outside.  
Alternate primary network interfaces for Intellect X to listen on.

<Ok>

8. ( ).

ITV Intellect X Server Configuration

Log level for Intellect X

0  
ERROR  
WARN  
INFO  
**DEBUG**  
TRACE  
ALL

<Ok>

9. .

ITV Intellect X Server Configuration

Enter host for ITV Intellect X DB. Leave it empty or set to the \_\_KEEP\_\_ to keep the value unmodified.

Intellect X DB host

localhost

<Ok>

10. .

ITV Intellect X Server Configuration

Enter TCP-port which ITV Intellect X DB listens to. Leave it empty or set to the \_\_KEEP\_\_ to keep the value unmodified.

Intellect X DB port

20110

<Ok>

11. , ( ).

ITV Intellect X Server Configuration

Remove rotated logs older than <count> days

7

<Ok>

12. , ( ).

ITV Intellect X Server Configuration

Log maximum size (in MiB)

100

<Ok>

